

MultiLogger Suite Release Report

Release: 5.1.3

Completed Items

Number Entered	Completed	Type	Application	Version	Description	
1845	9-1-2010	2-25-2011	Enhancement	MultiLogger	5.1.3	When renaming datalogger nodes prompt user to change nodename path, update Project Path as needed.
1922	1-15-2011	2-15-2011	Bug	MultiLogger	5.1.3	When selecting a different Gateway folder then automatically load that Gateway folder when returning to the Network Manager.
1923	1-15-2011	2-15-2011	Enhancement	MultiLogger	5.1.3	When configuring new Gateway folders leave password blank to disable required entry of password to enter Configuration Mode. To use Configuration Mode user has to configure a password for the Gateway Folder.
1937	2-4-2011	2-15-2011	Bug	MultiLogger	5.1.3	Disable all ML program generation options when selecting Download Files that don't match the default ML created Download File. This includes Zero & Test buttons, as well as buttons on Program tab, as well as Data Output, Alarm Action & Output Device
1938	2-4-2011	2-15-2011	Bug	MultiLogger	5.1.3	Don't compile programs when using Update function with custom Download Files.
1939	2-4-2011	2-15-2011	Enhancement	MultiLogger	5.1.3	When specifying alternate programs for Download File retrieve Public table definitions from logger directly. For legacy loggers continue to map available Text Monitor locations using DLD file.
1940	2-4-2011	2-15-2011	Enhancement	MultiLogger	5.1.3	When specifying alternate programs support all the fields supported by the CR2xx/CR800/CR1000.
1750	5/1/2009	2-15-2011	Enhancement	MLGateway	5.1.3	Improve recovery mechanism for CR2xx, CR800, CR1000 dropped connections, whether for modem, socket or COM. Recovery is very slow for any dropped connection, e.g. lost socket connections, lost com port, lost modem connection.
1819	11-1-2008	2-15-2011	Enhancement	MLGateway	5.1.3	Convert CR200/800/1000 data collection to use date/time in table arrays for Y1900 value for data import. Disable Y1900 option on data collection for these nodes.
1893	11-19-2010	2-15-2011	Enhancement	MLGateway	5.1.3	Add option to use Table date/time for CR2xx, CR800 & CR1000 instead of requiring storage of legacy date/time formats.
1934	2-4-2011	2-15-2011	Bug	MLGateway	5.1.3	When selecting alternate Download Files and the file is not in the Project Path then automatically copy it to the project path. Right now an error displays "File not found" after selecting the file.

MultiLogger Suite Release Report

Release: 5.1.3

Completed Items

Number Entered	Completed	Type	Application	Version	Description	
1944	2-7-2011	2-15-2011	Enhancement	MLDatabase	9.0.2	Add import of SAA data. Support automatic construct of Group using Serial Number, import elements using SAA_Xn (or Y, Z) format, where n = sequence number (data proceeds from bottom to top in file) and set ID for all elements to Serial Number.
1946	2-7-2011	2-15-2011	Bug	MLDatabase	9.0.2	Resolve issue with "blocking" when MLServer is running and a large import is running.
1949	2-1-2011	2-15-2011	Enhancement	MLDatabase	9.0.2	Add support for importing SAA data as modified Inclinator Instrument type. Use instrument serial number as Instrument & Group name.
1941	1-28-2011	2-15-2011	Enhancement	Insite	10.0.3	Add "null" button to operator buttons on Formula Editor.
1942	1-28-2011	2-15-2011	Bug	Insite	10.0.3	Occasionally thumbnails are not spaced properly in thumbnail viewer.
1945	2-7-2011	2-15-2011	Enhancement	Insite	10.0.3	Modify Inclinator support to recognize and work with SAA data, this includes utilizing single axis values for A & B (named X & Y) and using Z as depths. Default units for X, Y, Z are millimeters. Reduce supported Plot Type list to Cumulative
1950	8-1-2010	2-15-2011	Enhancement	MLWeb	6.1.3	Add support for reducing and presenting SAA data using modified Inclinator options.
1958	3-22-2011	2-15-2011	Bug	MLWeb	6.1.3	Fixed problem with MLWeb, happening when several sites are hosted on the same server, some sites would not start.
1918	2-1-2011	2-15-2011	Enhancement	MLServer	6.1.2	Add support for generation of SAA charts.
1943	2-7-2011	2-22-2011	Enhancement	MLServer	6.1.2	Add Filter to DB Import grid to allow selecting specific files or entering a file filter for import of data. Set filter default to *.dat *.csv, if filter is blank then no files are imported. Remove restriction on exe's in the import folder but continue to exclude root
1947	2-7-2011	2-15-2011	Bug	MLServer	6.1.2	Resolve issue with "blocking" when MLServer is running and a large import is running.

MultiLogger Suite Release Report

Release: 5.1.3

Completed Items

Number Entered	Completed	Type	Application	Version	Description	
1951	2-7-2011	2-15-2011	Bug	MLServer	6.1.2	Fix issue with broken calculations stopping processing of all calculations.